


How to Update the License-Server


For NX2212 and higher at least the license server version 2.1.0 is required.

For the installation you need the software `Siemens_LicenseServer_v2.1.0.0_Win64_x86-64.exe` and your current license.


You can download this for example in your [SIEMENS Support Center](#).

 `Siemens_LicenseServer_v2.1.0.0_Win64_x86-64.exe`


Run the file to start the update installation.




Choose the language for the installation setup and click OK.




Click Next.




Click Next.




Click Next.




Click Next.



Click Done if you want to adjust the license file manually and leave the installation. By default, it may be necessary to modify it. Therefore, we strongly recommend that you use the software to update the license. To do this, please click Licensing.




Click Licensing.




Navigate to your NX license file and select it.


Click Next.




Click Yes.



Click Next.



Click Next.




Click Done.

Congratulations, your installation is complete and you should now be able to use NX.


Alternative way to update the License via Add/Replace:

Run the file to start the license installation, as shown above.




Select Add/Replace License File.

Click Next.




Navigate to your NX license file and select it.


Click Next.




Click Yes.



Click Next.



Click Next.



Click Done.

Congratulations, your installation is complete and you should now be able to use NX.


Although this is a new service, many things remain the same for now:

- However, new default port is 29000 for lmgrd, and 29001 for saltd....
- If one of the obsolete services exists, it will be migrated to saltd. No duplicate services on the same server are possible. During migration, existing ugslmd files are "rewritten" to saltd, but continue to function.
- Licenses and logs are no longer referenced to the installation directory, but to "%ProgramData%\Siemens\License Server".

The following entries are changed:





```
#####
#
#
#           Siemens DISW Software Inc.
#           License File
#
# Site Location: [redacted]           Site: [redacted]
# Contact Name: [redacted]           Install: [redacted]
# Customer Name: [redacted]          Created: [redacted]
# E-mail Address: [redacted]          Version: [redacted]
#####
SERVER [redacted] COMPOSITE=( [redacted] 29000
VENDOR salted salted PORT=29001
```

In addition, the paths are adapted accordingly:



“%ProgramData%\Siemens\License Server” now contains the data, no longer as in the past the installation directory.

Name

-  ActiveLicenses
-  salted.log
-  slimtasks.json
-  slimusers.json